

MICRO ACCESS C Server/Client Configuration


1. Install MS SQL Express in MICRO ACCESS C server PC

A. Software required : Install below software


SQLEXPRESS_ENG_X64.EXE or SQLEXPRESS_ENG_X86.EXE



SQLServer2005_SSMSEE_ENG_x64.msi or SQLServer2005_SSMSEE_ENG_x86.msi


B. Run “SQL Server Configuration Manager”




C. Configure protocol , IP and communication port










D. Run “SQL Server Surface Area Configuration”




E. Configure remote connection





F. Back to “SQL Server Configuration Manager” to restart server




G. Close “SQL Server Configuration Manager” and “SQL Server Surface Area Configuration”

H. Run “SQL Server Management Studio Express”





I. Configure database according



Use “Windows Authentication” to connect SQL server.






Set "Server Authentication"



Attach database.












Add new user or modify existing user for accessing database


Add



Modify "sa"







2. PC with MICRO ACCESS C Server software


A. Software/hardware required : Install below software and plug-in Dongle Key

Setup Micro Access C Server 2.2.1.38.exe (MICRO ACCESS C Server)


HASPUserSetup.exe (USB Dongle Key driver)

USB Dongle Key


B. Run MICRO ACCESS C Server Software






Enter password and click "Log in" (Default is blank)




C. Configure database connection









D. Configure communication port for MICRO ACCESS C Client









E. Add role and account for MICRO ACCESS C Client to login MICRO ACCESS C Server


Add role





Add account





3. PC with MICRO ACCESS C Client software

A. Software required : Install below software

Setup Client Micro Access C 2.2.0.13.exe (MICRO ACCESS C Client)


http://www.chiyu-t.com.tw/program/files/files/Micro Access CCI_Setup.exe


B. Run MICRO ACCESS C Client



C. Connect MICRO ACCESS C Server


Click "Connection" to enter server IP and server port





Enter IP of PC with MICRO ACCESS C Server and port you set in MICRO ACCESS


If connection is through internet then please enable Check Box




Enter account and password created in MICRO ACCESS C Server

Click "Log in" to connect MICRO ACCESS C

Connect Fail



Connect Success



4. Connect Client to Server through Internet

- A. Open the port 1433 and 2002 at server router. Set the DDNS domain name in router.
- B. Client login with domain name.

